RSA SECURID® ACCESS Implementation Guide

Accompa

Gina Salvalzo, RSA Partner Engineering Last Modified: August 30, 2017



Solution Summary

Accompa is cloud-based Requirements Management software tool. It is widely used by Business Analysis, Product Management, Engineering, IT teams etc. Accompa delivers a single sign on experience to the user through SAML. This integration supports IdP initiated authentication flows.

RSA SecurID Access Features Accompa		
RSA SecurID	✓	
On Demand Authentication	✓	
Risk-Based Authentication (AM)	-	
Cloud Authentication Service Methods		
Authenticate App	✓	
FIDO Token	✓	
SSO		
SAML SSO	✓	
HFED SSO	-	

Identity Assurance	
Collect Device Assurance and User Behavior	√



Configuration Summary

All of the supported use cases of RSA SecurID Access with Accompa require both server-side and client-side configuration changes. This section of the guide includes links to the appropriate sections for configuring both sides for each use case.

RSA Cloud Authentication Service – Accompa can be integrated with RSA Cloud Authentication Service in the following way:

SAML via RSA Identity Router (IdP)

<u>Cloud Authentication Service – Identity Router IdP Configuration</u> <u>Accompa SAML Configuration</u>



RSA SecurID Access Server Side Configuration

RSA Cloud Authentication Service Configuration

SAML via RSA Identity Router (IdP)

To configure a SAML Service Provider in RSA Identity Router, you must deploy the connector for Accompa in the RSA SecurID Access Console. During configuration of the IdP you will need some information from the SP. This information includes (but is not limited to) Assertion Consumer Service URL and Service Provider Entity ID.

Configure RSA Identity Router SAML IdP

Procedure

- 1. In the RSA SecurID Access Administration Console, click **Applications > Application Catalog**.
- 2. From the list of applications, click +Add Accompa.




Accompa SAML Direct







3. On the Basic Information page, specify the application name and click **Next Step**.




- 4. Navigate to **Initiate SAML Workflow** section.
 - a. In the **Connection URL** field, keep the field blank as the value is not required.
 - b. Choose IDP-initiated.







5. Scroll down to **SAML Identity Provider (Issuer)** section.



- a. Make a note of **Identity Provider URL** field value, as it will be needed later to configure the Service Provider configuration.
- b. Select **Default (idp_id)** for value for the **Issuer Entity ID**. Make sure that same **Issuer ID** is provided at SP-side SAML configuration.
- c. Select **Choose File** and upload the private key.
- d. Select **Choose File** to import the public signing certificate.
- e. Select the checkbox for Include Certificate in Outgoing Assertion.




6. Scroll down to the **Service Provider** section.

Assertion Consumer Service (ACS) URL https://www.accompa.com/samlsp/module.php/saml/sp/saml2-acs.php/saml-sso-sp Audience (Service Provider Entity ID) https://www.accompa.com/samlsp

- a. In the Assertion Consumer Service (ACS) URL field, provide the value as per received.
- b. In the Audience (Service Provider Issuer ID) field, provide the value as per received.
- 7. Scroll down to the **User Identity** section. Verify the settings are correct for your environment. In this example the username to be presented in email format and the user account will be validated against the User Store selected.



 Moving next, select Show Advanced Configuration. In the Attribute Extension section, add email. These are mandatory provisioning attributes needs to be forwarded at the time of SSO.



9. Click Next Step.



10. On the **User Access** page, select **Allow All Authenticated Users** user policy from the available options.

Select the access policy to determine which users are allowed to access the application. Allow All Authenticated Users Select Custom Policy No Access Allowed

- 11. Click Next Step.
- 12. On the **Portal Display** page, select **Display in Portal**.
- 13. Click Save and Finish.
- 14. Click **Publish Changes**. Your application is now enabled for SSO.





Partner Product Configuration

Before You Begin

This section provides instructions for configuring the Accompa with RSA SecurID Access. This document is not intended to suggest optimum installations or configurations.


It is assumed that the reader has both working knowledge of all products involved, and the ability to perform the tasks outlined in this section. Administrators should have access to the product documentation for all products in order to install the required components.

All Accompa components must be installed and working prior to the integration. Perform the necessary tests to confirm that this is true before proceeding.

Accompa SAML Configuration


Procedure

- 1. Login to your Accompa application web account. (https://www.accompa.com/login.html)
- Following UI will be displayed. Go to Settings → Configure SAML SSO.





3. Following UI will be displayed. Navigate to Configure SAML SSO (Single Sign-On) section.



- a. Make a note of Accompa SSO Login URL and Entity ID values.
 These will be handy during IdP side SSO configurations.

 Note: These values are generated after completion of SAML configuration.
- b. Select Users can login using SSO or Accompa login page radio button for the Restrict to SSO Only field so that users will not be locked out to login manually inside account in the scenarios of SSO failures.
- c. **Issuer**: Provide IdP issuer value here received from step 5b page 6.
- d. **Identity Provider Certificate**: Provide public certificate of IDR refer to step 5d page 6.
- e. **Request Signature Method**: Choose appropriate signing mechanism from available drop-down options.
- f. Identity Provider Login URL: Enter the Identity Provider URL which can be found in step 5a on page 3. It is of following format: ?idp_id=<unique_IdP_ID>">https://cyour_portal_uRL>?idp_id=<unique_IdP_ID>
- g. **Identity Provider Logout URL**: Provide URL value where users will get redirected after logging out from the account.
- h. **Custom Error URL**: Provide URL value for landing page for the users in case of SSO failure.
- i. Click on the **Save** button to configure SAML settings.
- 4. Navigate to Settings > Manage Users.
- 5. Add user.

