

RSA NetWitness Logs

Event Source Log Configuration Guide



Cisco Secure IDS or IPS

Last Modified: Wednesday, October 4, 2017

Event Source Product Information:

Vendor: [Cisco](#)

Event Source: Secure Intrusion Prevention System (IPS)

Versions: 4.x, 5.0, 5.1, 6.0, 6.1, 6.2, 7.x

Note: RSA is qualifying support for the major version. In case of any configuration changes or logs not parsing in a minor version, please open a case and we will add support for it.

Signature Engines: E1, E2, E3, E4

RSA Product Information:

Supported On: NetWitness Suite 10.0 and later

Event Source Log Parser: ciscoidsxml

Collection Method: SDEE

Event Source Class.Subclass: Security.IDS

Configure Secure Cisco IDS/IPS

To set up Cisco Secure IDS or IPS to work with RSA NetWitness Suite, perform the following tasks:

- I. Configure Cisco Secure IDS/ IPS
- II. Configure the Log Collector for SDEE Collection

Configure the Cisco Secure IDS/IPS event source

Configure RSA NetWitness Suite to access the sensor, apply an access list to the sensor.

On the Cisco Secure IDS/IPS event source, follow these steps:

1. Log on to the Cisco Secure IDS/IPS console, using administrative credentials.
2. Type the following commands:

```
configure terminal
service host
network-settings
```
3. Use the access-list command to allow RSA NetWitness Suite to access the sensor. Type the following commands:

```
access-list IP address of the RSA NetWitness Suite Log Collector
```

For example, to allow a host access, type **access-list 1.2.3.4/32**, or to allow a network access, type **access-list 1.2.3.0/24**.
4. Exit the configuration mode, confirming to save changes when prompted

Configure the Log Collector for SDEE Collection


You should configure the Log Collector for SDEE collection.

To configure the Log Collector for SDEE collection:

1. In the Security Analytics menu, select **Administration > Services**.
2. In the Services grid, select a Log Collector, and from the Actions menu, choose **View > Config > Event Sources**.
3. Select **SDEE/Config** from the drop-down menu.

The Event Categories panel displays the SDEE event sources that are configured, if any.
4. In the Event Categories panel toolbar, click **+**.


The Available Event Source Types dialog is displayed.



Select **ciscoids** from the **Available Event Source Types** dialog.

5. Select the correct type from the list, and click **OK**.

The newly added event source type is displayed in the Event Categories panel.



6. Select the new type in the Event Categories panel and click **+** in the Sources panel toolbar.

The Add Source dialog is displayed.

Add Source

Basic

Name * ApacheSimulatorHost

Username * admin

Password *

Address * simv6

Enabled

Certificate Name

Advanced

Port 443

SSL Version tlsv1

Include Raw Event Data

Save Raw XML Files

Saved File Quota 100 Megabyte

Subscription Event Types evidsAlert

Force Subscription

Subscription Severity Filter

Subscription Time Offset 0

Polling Interval 180

Max Events Poll 5000

Query Timeout 0

URL Parameters

URL Path /cgi-bin/sdee-server

URL Protocol https

Debug On

Cancel OK

7. Add a Name, Username, Address, and Password, and modify any other parameters that require changes, and click **OK**.

Copyright © 2017 EMC Corporation. All Rights Reserved.

Trademarks

RSA, the RSA Logo and EMC are either registered trademarks or trademarks of EMC Corporation in the United States and/or other countries. All other trademarks used herein are the property of their respective owners.