

RSA NetWitness Platform

Event Source Log Configuration Guide



McAfee Data Loss Prevention Endpoint

Last Modified: Tuesday, November 20, 2018

Event Source Product Information:

Vendor: [McAfee](#)

Event Source: Data Loss Prevention Endpoint (formerly known as Host DLP)

Versions: 2.2, 3.0, 9.0, 9.1, 9.2, 9.3, 9.4.x, 10.x

Note: RSA is qualifying support for the major version. In case of any configuration changes or logs not parsing in a minor version, please open a case and we will add support for it.

RSA Product Information:

Supported On: NetWitness Platform 10.0 and later

Event Source Log Parser: mcafeedlp

Collection Method: ODBC

Event Source Class.Subclass: Security.DLP

Configure McAfee Data Loss Prevention Endpoint

To configure McAfee Data Loss Prevention Endpoint you must configure RSA NetWitness Platform for ODBC collection:

- I. Ensure the required parser is enabled
- II. Configure a DSN
- III. Add the Event Source Type

Ensure the Required Parser is Enabled

If you do not see your parser in the list while performing this procedure, you need to download it in RSA NetWitness Platform Live.


Ensure that the parser for your event source is enabled:

1. In the **NetWitness** menu, select **ADMIN > Services**.
2. In the **Services** grid, select a **Log Decoder**, and from the **Actions** menu, choose **View > Config**.
3. In the **Service Parsers Configuration** panel, search for your event source, and ensure that the **Config Value** field for your event source is selected.

Note: The required parser is **mcafeedlp**.

Configure a DSN

Configure a DSN (Data Source Name):

1. In the **NetWitness** menu, select **ADMIN > Services**.
2. In the **Services** grid, select a **Log Collector** service.
3. Click  under **Actions** and select **View > Config**.
4. In the **Log Collector Event Sources** tab, select **ODBC/DSNs** from the drop-down menu.
5. The **DSNs** panel is displayed with the existing **DSNs**, if any.
6. Click **+** to open the **Add DSN** dialog.


Note: If you need to add a DSN template, see the "Configure DSNs" topic in the *Log Collection Configuration Guide*, available in [RSA Link](#).

7. Choose a DSN Template from the drop down menu and enter a name for the DSN. (You use the name when you set up the ODBC event source type.)
8. Fill in the parameters and click **Save**.

Field	Description
DSN Template	Choose the correct template from the available choices.
DSN Name	Enter a descriptive name for the DSN
Parameters section	
Database	Specify the database used by McAfee Data Loss Prevention Endpoint
PortNumber	Specify the Port Number. The default port number is 1433
HostName	Specify the hostname or IP Address of McAfee Data Loss Prevention Endpoint
Driver	Depending on your NetWitness Log Collector version: <ul style="list-style-type: none"> • For 10.6.2 and newer, use /opt/netwitness/odbc/lib/R3sqls27.so • For 10.6.1 and older, use /opt/netwitness/odbc/lib/R3sqls26.so


Add the Event Source Type

Add the ODBC Event Source Type:


1. In the **NetWitness** menu, select **ADMIN > Services**.
2. In the **Services** grid, select a **Log Collector** service.
3. Click  under **Actions** and select **View > Config**.
4. In the Log Collector **Event Sources** tab, select **ODBC/Config** from the drop-down menu.

The Event Categories panel is displayed with the existing sources, if any.

5. Click **+** to open the **Available Event Source Types** dialog.



6. Choose the log collector configuration type for your event source type and click **OK**.
 - For versions 9.4.x or 10.x, select **mcafeedlptvm**.
 - For versions 3.0, select **mcafeedlp3000**.
 - For version 2.2, select **mcafeedlp**.
7. In the **Event Categories** panel, select the event source type that you just added.
8. In the **Sources** panel, click **+** to open the **Add Source** dialog.



9. Enter the DSN you configured during the **Configure a DSN** procedure.

10. For the other parameters, see the "ODBC Event Source Configuration Parameters" topic in the *RSA NetWitness Platform Log Collection Guide*.

Copyright © 2018 Dell Inc. or its subsidiaries. All Rights Reserved.

Trademarks

For a list of RSA trademarks, go to www.emc.com/legal/emc-corporation-trademarks.htm#rsa.