



SecurID Authenticator for Windows Quick Start Guide

SecurID Authenticator enables you to authenticate with RSA Authentication Manager (AM) OTP credentials or cloud-based methods such as OTP, push to approve, fingerprint, or face recognition from a single app.

This document provides you with step-by-step instructions on how to install and use SecurID Authenticator.

What You Need

You need a Microsoft Windows computer to install the app. The device must have Microsoft Windows 10 1903 or later.

Your administrator should provide one of the following details for adding a credential:

- A URL to your company's self-service portal or SecurID My Page with instructions for registering the app, including a new Registration Code, or URL for each credential.
- Information to import a credential using a URL link, or email attachment, and a password if required.

Step 1: Install SecurID Authenticator


1. On your Windows computer, open Microsoft Store.
2. Search for **SecurID Authenticator**, which looks like this:



3. Install the app.

Step 2: Import Your SecurID Credential

1. Open **SecurID Authenticator**.
2. Click **Add Credential** and follow the prompts.

If you already imported a credential, click  (**Add Credential**) to add more. Your administrator needs to provide you with credential details for each credential.

Your credential is now active.


Step 3: Sign in to Applications

You can use your SecurID OTP credentials to sign in to applications such as VPN clients or applications.

Tip: Click an OTP to copy it to an application on the same Windows computer.

1. On your Windows computer, open the VPN client or application.
2. Enter your username. Leave the sign-in screen open.
3. Open **SecurID Authenticator**.
4. If you have added a SecurID AM OTP credential, follow the below steps:

If your credential displays Enter SecurID PIN:



- a. Enter your PIN and then click **Submit** to view the OTP.
- b. In the VPN client or application window, enter the OTP without any spaces.
- c. Click **OK**.

If your credential looks like this:




- a. Enter one of the following in the VPN client or application window:
 - If you have a PIN, enter the PIN followed by the SecurID OTP without any spaces.
 - If you do not need a PIN, enter only the SecurID OTP without any spaces.
- b. Click **OK**.

Step 4: Register the App

SecurID Authenticator for Windows helps you access your company's protected resources by providing multifactor authentication with Approve (push notifications), OTP, and Biometrics. If you will use these authentication methods, you must register your Windows computer.

Your administrator should have sent you a link to access your organization's self-service portal or My Page.

SecurID My Page	Your Organization's Self-Service Portal
<ol style="list-style-type: none">1. Open a browser and access the portal using the link your administrator provided.2. Log in to SecurID My Page. 3. If the SecurID Authenticator is already listed as registered, you must de-register it by clicking the Trash icon.4. Click Register an authenticator and then select SecurID Authenticator from the list.5. Follow the on-screen prompts to complete registration.6. Test authentication.	<ol style="list-style-type: none">1. Open a browser and access the portal using the link your administrator provided.2. Follow your organization's registration instructions.3. Test authentication.

Want to Learn More?

See https://help.access.securid.com/EN_US/index.html for more information about how to use SecurID Authenticator.